

Modal de Géophysique
The double bucket method to create a stratification

bruno.deremble@ens.fr

We wish to create a linear vertical stratification:

$$N^2 = -\frac{g}{\rho_0} \frac{\partial \rho}{\partial z} = \text{cte}. \quad (1.1)$$

1. Make sure the valves *A* and *B* are closed
2. Fill up two tanks: one with fresh water and one with salty water. The water level in the two tanks should be identical. You can control the value of N^2 by adjusting the volume of water in the fresh and salt water tanks and the salt concentration. Carefully adjust these parameters and measure the salt concentration with the refractometer.
3. Start the stirrer in the fresh water tank so that it remains well mixed.
4. Open the valve *A* to its maximum.
5. You are going to fill up your tank for your experiment from the bottom. Adjust and attach the fresh water discharge tube such that it will always remain at the bottom of your tank (in the middle if possible).
6. Slowly open valve *B* to minimize the turbulence at the outlet of the tube.




Figure 1.1: Illustration of the double bucket method